

<u>Source</u>	<u>SS</u>
Model	187
Error	8
C. Total	195

<u>Source</u>	<u>Type I SS</u>
X1	144
X2	22
X3	21

<u>Source</u>	<u>Type III SS</u>
X1	10
X2	37
X3	21

<u>Source</u>	<u>SS</u>
Model	187
Error	8
C. Total	195

<u>Source</u>	<u>Type I SS</u>
X1	144
X2	22
X3	21

<u>Terms in Model</u>	<u>SSE</u>	<u>Decrease</u>
none	195	
X1	51	144
X1, X2	29	22
X1, X2, X3	8	21

<u>Source</u>	<u>SS</u>
Model	187
Error	8
C. Total	195

<u>Source</u>	<u>Type III SS</u>
X1	10
X2	37
X3	21

<u>Terms in Model</u>	<u>SSE</u>
X1, X2, X3	8
X2, X3	18
X1, X3	45
X1, X2	29

Adding X1 to the model that already has X2 and X3 reduces the SSE by 10.

Adding X2 to the model that already has X1 and X3 reduces the SSE by 37.

Adding X3 to the model that already has X1 and X2 reduces the SSE by 21.

A difference of 37.
